
Gearthonic Documentation

Release 0.2.0

Timo Steidle

August 08, 2016

1	Quickstart	3
2	Contents:	5
2.1	Usage	5
2.2	API	6
2.3	Contributing	10
2.4	Changelog	12
3	Feedback	13
	Python Module Index	15

A simple client for the API of Homegear.

Look at the [documentation](#) for detailed information.

Quickstart

Install *gearthonic* via pip:

```
pip install gearthonic
```

Initialise the client:

```
from gearthonic import GearClient
# You only have to provide the host and port of the Homegear server
gc = GearClient('192.168.1.100', 2001, secure=False, verify=False)
```

Use the predefined methods to make requests to the API:

```
gc.system.list_methods()
gc.device.get_value(1, 4, 'ACTUAL_TEMPERATURE')
```

Alternatively you can call any method directly via the client:

```
gc.getValue(1, 4, 'ACTUAL_TEMPERATURE')
```

The default communication protocol is XML-RPC. If you want to use another protocol like JSON-RPC or a MQTT broker, see the full [documentation](#).

Contents:

2.1 Usage

2.1.1 Basic usage

To use Gearthonic in a project:

```
from gearthonic import GearClient
# Initialise the client with the host and port of your homegear server
gc = GearClient('192.168.1.100', 2003)
# Now you can make your requests
gc.system.list_methods()
gc.device.get_value(1, 4, 'ACTUAL_TEMPERATURE')
```

All methods are already implemented within the client to make it easy to use. You don't have to lookup all methods and their parameters, just look at the code or see [Method Reference](#).

Alternatively you can call any method directly via the client or use the generic "call"-method:

```
gc.getValue(1, 4, 'ACTUAL_TEMPERATURE')
gc.call('system.listDevices')
gc.call('getValue', 1, 4, 'ACTUAL_TEMPERATURE')
```

A full list of all available methods provided by the Homegear API can be found in the [wiki](#) of the Homegear project.

2.1.2 Communication protocols

Gearthonic supports different communication protocols to communicate with your Homegear server. Set the protocol while initialising the client:

```
from gearthonic import JSONRPC
gc = GearClient('192.168.1.100', 2003, protocol=JSONRPC)
```

The default protocol is XMLRPC.

Any protocol can accept additional parameters. You can supply them while initialising the client:

```
gc = GearClient('192.168.1.100', 2003, secure=False, verify=False)
```

For a complete list of available protocols and supported parameters look at [gearthonics.protocols](#).

2.1.3 Security

XML RPC and JSON RPC

If you set `secure=True` while initialising the `GearClient`, the client tries to establish a secure connection to the server via SSL. It's highly recommended to use SSL for the network traffic. Otherwise the communication is not encrypted.

If you are using a self signed certificate, you can skip the verification of the certificate. Set `verify=False` while initialising the `GearClient` and the certificate won't be verified. But keep in mind: that's not suggested!

2.1.4 Additional information

- Documentation of all available data endpoints for all devices
- wiki of the Homegear project

2.2 API

2.2.1 API Reference

See [Method Reference](#) for all API methods.

GearClient

Client for the APIs provided by Homegear.

```
class gearhonic.client.GearClient(host, port, protocol=0, **kwargs)
```

Client for the APIs provided by Homegear.

Usage:

```
>>> gc = GearClient('localhost', 1234)
>>> gc.device.list_devices()
```

The default communication protocol is XML RPC. Additionally, JSON RPC is supported:

```
>>> from gearhonic import JSONRPC
>>> GearClient('localhost', 1234, protocol=JSONRPC)
```

Any protocol can accept additional parameters. Provide them while initialising the client:

```
>>> GearClient('localhost', 1234, protocol=JSONRPC, secure=False, username='ham')
```

For a full list of supported parameters, have a look at each protocol class or see the documentation for the protocols. :class:

```
call(method_name, *args, **kwargs)
```

Call the given method using the instantiated protocol.

Parameters

- `method_name` – method to be called
- `args` – arguments passed through
- `kwargs` – keyword arguments passed through

Returns return value of the call

device

Smart access to all device related API methods.

system

Smart access to all system related API methods.

Communication protocols

These classes are used to communicate with the different APIs provided by the Homegear server.

```
class gearthonic.protocols.JsonRpcProtocol(host, port, secure=True, verify=True, username=None, password=None)
```

Communicate with Homegear via JSON RPC.

```
>>> jp = JsonRpcProtocol('host.example.com', 2003)
>>> jp.call('listDevices')
[...]
```

Set `secure=False` to use `http` instead off `https`. Set `verify=False` to skip the verification of the SSL cert.

Provide credentials via `username` and `password` if the Homegear server is secured by basic auth. It's not possible to use authentication with an insecure connection (`http`)!

```
call(method_name, *args, **kwargs)
```

Call the given method using the HTTPServer.

Parameters

- **method_name** – Method to be called
- **args** – Arguments passed through
- **kwargs** – Keyword arguments passed through

Returns Return value of the XML RPC method

```
class gearthonic.protocols.XmlRpcProtocol(host, port, secure=True, verify=True, username=None, password=None)
```

Communicate with Homegear via XML RPC.

```
>>> xp = XmlRpcProtocol('host.example.com', 2003)
>>> xp.call('listDevices')
[...]
```

Set `secure=False` to use `http` instead off `https`. Set `verify=False` to skip the verification of the SSL cert.

Provide credentials via `username` and `password` if the Homegear server is secured by basic auth. It's not possible to use authentication with an insecure connection (`http`)!

```
call(method_name, *args, **kwargs)
```

Call the given method using the ServerProxy.

Parameters

- **method_name** – Method to be called
- **args** – Arguments passed through
- **kwargs** – Keyword arguments passed through

Returns Return value of the XML RPC method

```
gearthonic.protocols.initialise_protocol(protocol, host, port, **kwargs)
```

Factory method to initialise a specific protocol.

Parameters

- **protocol** (*int*) – ID of the protocol to initialise
- **host** (*str*) – host of the server
- **port** (*int*) – port of the server
- **kwargs** – will be used to initialise the protocol

Return type _ProtocolInterface

2.2.2 Method Reference

System methods

```
class gearthonic.methods.SystemMethodsCollection(caller)
```

All XML RPC server provide a set of standard methods.

```
get_capabilities()
```

Lists server's XML RPC capabilities.

Example output:

```
{  
    'xmlrpc': {'specUrl': 'http://example.com', 'specVersion': 1}  
    'faults_interop': {'specUrl': 'http://example2.com', 'specVersion': 101}  
    'introspection': {'specUrl': 'http://example3.com', 'specVersion': 42}  
}
```

Returns A dict containing all information

Return type dict

```
list_methods()
```

Lists servers's XML RPC methods.

Returns A list of available methods

Return type list

```
method_help(method_name)
```

Returns the description of a method.

Parameters **method_name** (*str*) – The name of the method

Returns The description of the method

Return type str

```
method_signature(method_name)
```

Returns the signature of a method.

Parameters **method_name** (*str*) – The name of the method

Returns The signature of the method

Return type list

multicall (methods)
Call multiple methods at once.

Example list of methods:

```
[  
    {'methodName': 'getValue', 'params': [13, 4, 'TEMPERATURE']},  
    {'methodName': 'getValue', 'params': [3, 3, 'HUMIDITY']}  
]
```

Return value of the multicall:

```
[22.0, 58]
```

Parameters **methods** (*list*) – A list of methods and their parameters

Returns A list of method responses.

Return type list

Device methods

class gearthonic.methods.**DeviceMethodsCollection** (*caller*)

All device related methods.

activate_link_paramset (*peer_id*, *channel*, *remote_peer_id*, *remote_channel*, *long_pressed=False*)

Returns

get_value (*peer_id*, *channel*, *key*, *request_from_device=False*, *asynchronous=False*)

Return the value of the device, specified by channel and key (parameterName).

Per default the value is read from the local cache of Homegear. If the value should be read from the device, use *request_from_device*. If the value should be read from the device, this can be done asynchronously. The method returns immediately and doesn't wait for the current value. The value will be sent as an event as soon as it's returned by the device.

Error codes:

- Returns -2 when the device or channel is unknown
- Returns -5 when the key (parameter) is unknown

Parameters

- **peer_id** (*int*) – ID of the device
- **channel** (*int*) – Channel of the device to get the value for
- **key** (*str*) – Name of the parameter to get the value for
- **request_from_device** (*bool*) – If true value is read from the device
- **asynchronous** (*bool*) – If true value is read asynchronously

Returns The value of the parameter or error code

Return type unknown

list_devices ()

Return a list of devices.

Returns List of devices

Return type list

set_value (*peer_id*, *channel*, *key*, *value*)

Set the value of the device, specified by channel and key (parameterName).

Parameters

- **peer_id** (*int*) – ID of the device
- **channel** (*int*) – Channel of the device to set the value for
- **key** (*str*) – Name of the parameter to get the value for
- **value** (*unknown*) – The value to set

Returns

- None on success
- -2 when the device or channel is unknown
- -5 when the key (parameter) is unknown
- -100 when the device did not respond
- -101 when the device returns an error

2.3 Contributing

Contributions are welcome, and they are greatly appreciated! Every little bit helps, and credit will always be given.

You can contribute in many ways:

2.3.1 Types of Contributions

Report Bugs

Report bugs at <https://gitlab.com/wumpitz/gearthonic/issues>.

If you are reporting a bug, please include:

- Your operating system name and version.
- Any details about your local setup that might be helpful in troubleshooting.
- Detailed steps to reproduce the bug.

Fix Bugs

Look through the Gitlab issues for bugs. Anything tagged with “bug” is open to whoever wants to implement it.

Implement Features

Look through the Gitlab issues for features. Anything tagged with “feature” is open to whoever wants to implement it.

Write Documentation

Gearhonic could always use more documentation, whether as part of the official gearhonic docs, in docstrings, or even on the web in blog posts, articles, and such.

Submit Feedback

The best way to send feedback is to file an issue at <https://gitlab.com/wumpitz/gearhonic/issues>.

If you are proposing a feature:

- Explain in detail how it would work.
- Keep the scope as narrow as possible, to make it easier to implement.
- Remember that this is a volunteer-driven project, and that contributions are welcome :)

2.3.2 Get Started!

Ready to contribute? Here's how to set up *gearhonic* for local development.

1. Fork the *gearhonic* repo on Gitlab.
2. Clone your fork locally:

```
$ git clone git@gitlab.com:your_name_here/gearhonic.git
```

3. Create a branch for local development:

```
$ git checkout -b name-of-your-bugfix-or-feature
```

Now you can make your changes locally.

4. When you're done making changes, check that your changes pass style and unit tests, including testing other Python versions with tox:

```
$ tox
```

To get tox, just pip install it.

5. Commit your changes and push your branch to Gitlab:

```
$ git add .
$ git commit -m "Your detailed description of your changes."
$ git push origin name-of-your-bugfix-or-feature
```

6. Submit a pull request through the Gitlab website.

2.3.3 Pull Request Guidelines

Before you submit a pull request, check that it meets these guidelines:

1. The pull request should include tests.
2. If the pull request adds functionality, the docs should be updated. Put your new functionality into a function with a docstring, and add the feature to the list in README.rst.
3. The pull request should work for Python 2.7 and 3.5, and for PyPy. Run the `tox` command and make sure that the tests pass for all supported Python versions.

2.3.4 Tips

To run a subset of tests:

```
$ py.test test/test_gearthonic.py
```

2.4 Changelog

2.4.1 0.2.0 (2016-08-08)

- Introduced different communication protocols (XML RPC and JSON RPC)

2.4.2 0.1.2 (2016-07-13)

- Fixed broken setup.py.

2.4.3 0.1.1 (2016-07-13)

- Added documentation.

2.4.4 0.1.0 (2016-07-13)

- Initial release to pypi.

Feedback

If you have any suggestions or questions about **gearthonic** feel free to email me at mumpitz@wumpitz.de.

If you encounter any errors or problems with **gearthonic**, please let me know! Open an Issue at the Gitlab <http://gitlab.com/wumpitz/gearthonic> main repository.

g

`gearthonic.client`,⁶
`gearthonic.protocols`,⁷

A

activate_link_paramset() (gearthonic.methods.DeviceMethodsCollection method), 9

C

call() (gearthonic.client.GearClient method), 6
call() (gearthonic.protocols.JsonRpcProtocol method), 7
call() (gearthonic.protocols.XmlRpcProtocol method), 7

D

device (gearthonic.client.GearClient attribute), 7
DeviceMethodsCollection (class in gearthonic.methods), 9

G

GearClient (class in gearthonic.client), 6
gearthonic.client (module), 6
gearthonic.protocols (module), 7
get_capabilities() (gearthonic.methods.SystemMethodsCollection method), 8
get_value() (gearthonic.methods.DeviceMethodsCollection method), 9

I

initialise_protocol() (in module gearthonic.protocols), 8

J

JsonRpcProtocol (class in gearthonic.protocols), 7

L

list_devices() (gearthonic.methods.DeviceMethodsCollection method), 9
list_methods() (gearthonic.methods.SystemMethodsCollection method), 8

M

method_help() (gearthonic.methods.SystemMethodsCollection method), 8
method_signature() (gearthonic.methods.SystemMethodsCollection method), 8

multicall() (gearthonic.methods.SystemMethodsCollection method), 8

S

set_value() (gearthonic.methods.DeviceMethodsCollection method), 10
system (gearthonic.client.GearClient attribute), 7
SystemMethodsCollection (class in gearthonic.methods), 8

X

XmlRpcProtocol (class in gearthonic.protocols), 7